

Security Fabric CLI Commands:

Use the following commands to view, accept, and deny authorization requests, to view upstream and downstream units, and to list or test fabric units:

Commands	Description
diagnose sys csf authorization pending-list	View pending authorization requests on the root FortiGate
diagnose sys csf authorization accept FGVMEVK0QOGGCK0E	Authorize a device to join the Security Fabric
diagnose sys csf authorization pending-list	View pending authorization requests on the root FortiGate
diagnose sys csf authorization deny FGVMEVK0QOGGCK0E	Deny a device from joining the Security Fabric
diagnose sys csf downstream	Show connected downstream devices
diagnose sys csf upstream	Show connected upstream devices
diagnose sys csf fabric-device list	List all known fabric devices

```
✓ HQ-FW x
HQ-FW #
HQ-FW # diagnose sys csf authorization pending-list
Serial                               IP Address                          HA-Members
-----
HQ-FW # diagnose sys csf authorization pending-list
Serial                               IP Address                          HA-Members
-----
FGVMEVK0QOGGCK0E                    192.168.100.205:443
CK0E
```

```
✓ HQ-FW x
HQ-FW #
HQ-FW # diagnose sys csf downstream
1: FGVMEVK0QOGGCK0E (192.168.100.205) Management-IP: 192.168.100.205 M
   path: FGVMEVA8B-NG085A:FGVMEVK0QOGGCK0E
   data received: Y downstream intf:port5 upstream intf:port5 upstream
   admin-port:443 authorizer:FGVMEVA8B-NG085A
2: FGVMEVNERDJ6KE6E (192.168.100.230) Management-IP: 192.168.100.230 M
   path: FGVMEVA8B-NG085A:FGVMEVNERDJ6KE6E
   data received: Y downstream intf:port5 upstream intf:port5 upstream
   admin-port:443 authorizer:FGVMEVA8B-NG085A
3: FGVMEVJAIWYL3H5B (192.168.100.220) Management-IP: 192.168.100.220 M
   path: FGVMEVA8B-NG085A:FGVMEVJAIWYL3H5B
   data received: Y downstream intf:port5 upstream intf:port5 upstream
   admin-port:443 authorizer:FGVMEVA8B-NG085A
```

✓ HQ-FW ✓ FW1 ✕

```
FW1 # diagnose sys csf upstream
Upstream Information:
Serial Number:FGVMEVA8B-NG085A
IP:192.168.100.200
Connecting interface:port5
Connection status:Authorized
```

✓ HQ-FW ✓ FW1 ✓ DC-FW ✕ ✓ BR-FW

```
DC-FW #
DC-FW # diagnose sys csf upstream
Upstream Information:
Serial Number:FGVMEVA8B-NG085A
IP:192.168.100.200
Connecting interface:port5
Connection status:Authorized
```

✓ HQ-FW ✓ FW1 ✓ DC-FW ✓ BR-FW ✕

```
BR-FW #
BR-FW # diagnose sys csf upstream
Upstream Information:
Serial Number:FGVMEVA8B-NG085A
IP:192.168.100.200
Connecting interface:port5
Connection status:Authorized
```